

3M™ Know Your Air Software for the Multi-Gas Detector 950 Series - CONFIGURATION OPTIONS

Detector configuration information can be transferred between the 950 Series Detector and 3M Know Your Air software thus allowing for the selection of specific options via the detector or the software. Initiate communication between the 950 Series Detector and PC by pressing the *Config.* button. This results in a download of the specific configuration of that detector to the software program.

General Options

In the KNOW YOUR AIR PC Software, the “General” tab provides access to information about the detector and information displayed on the LCD.

Making a change to a field in the Configuration menu will cause that field to be highlighted (yellow) until such time as the change has been successfully transferred to the detector. Pressing the *Reset* button will return all tentative changes to their original values.

By clicking on the “General Tab” the serial number and user changeable asset number will be displayed.

The Date and Time Section allow the user to:

- a) choose if date and time are displayed
- b) allow clock autosync to the PC

Under the Time Weighted Average Displays the user can:

- a) select the mode from one of four and
- b) display STEL and TWA as a percentage of alarm point.

Under the Buzzer Section, the user may:

- a) enable or disable the button click and 30 second beep.

Under the Auto Response Time the user may:

- a) set the time that the 950 waits for the SELECT key to be pressed.

Under the Backlight Section the mode can be changed to:

- a) on
- b) off
- c) automatic
- d) duration can be set.

Click “Configure” to send the changes to the detector. A window will appear warning that the changes will not take effect until the unit is restarted.

Clicking the “yes” button will turn off the unit. Once the unit is turned back on, all the changes will have been made.